Applying Safari 20 SG by Trunk Spray – Master Batch

IMPORTANT

Use the **specially marked measuring cup** that comes with your purchase of Safari to measure the required amount of product and a regular measuring cup to measure the amount of water. Note that the numbers printed on the special measuring cup refer to *ounces of weight* of Safari 20 SG and are *not* the same as *fluid ounces of volume* in a regular measuring cup.

CONVERSION FACTOR

If you don't have the special measuring cup, you can use a regular measuring cup with the following conversion factor for Safari 20 SG:

8 fl. oz. by volume in a regular measuring cup = 4 oz. by weight in the Safari measuring cup.

Wear long sleeved shirt, long pants, shoes and socks, goggles, gloves, and mask while spraying.

Step 1. To make a **master batch of treatment mixture**, put the required amount of water in a mixing container first.

Warm water works best. Then add the corresponding amount of product shown in the Mixing chart below and shake well until all treatment material is dissolved.

MIXING THE N	MIXING THE MASTER BATCH					
★ Amount of Product	Amount of Water					
3.5 ounces	32 fluid ounces (1 qt)					
7 ounces	64 fluid ounces (2 qts)					
10.5 ounces	96 fluid ounces (3 qts)					
12 ounces	110 fluid ounces					
14 ounces	128 fluid ounces (1 gal)					

Step 2. Measure the trunk diameter of the tree at breast height. This is called "inches dbh."

Step 3. Treatment is done on an **individual tree** basis. Use the Dosing table below to determine how many ounces of treatment mixture the tree needs by multiplying its trunk diameter by the number of ounces shown in the right-hand column. Use a regular measuring cup to measure out exactly the required amount of treatment mixture for the tree and pour it into the sprayer.


DOSING EACH TREE					
Inches (DBH)	Oz of TREATMENT MIXTURE PER INCH DBH				
1 - 15	1 ounce				
16 – 19	1.33 ounces				
20 - 23	1.67 ounces				
24 - 27	2 ounces				
28 - 31	2.33 ounces				
32 - 35	2.67 ounces				
36 – 39	3 ounces				
40 or greater	3.33 ounces				

Step 4. Set the sprayer for low pressure (10-15 psi) and adjust the nozzle for a spray about 3-4 inches wide (not a stream and not a mist). Position the nozzle 2 inches from the trunk and spray from 5 ½ feet above the ground to 6 inches above the ground. Do this very slowly to avoid back-splash and allow the treatment material to be absorbed into the bark; try not to let it drip down onto the ground if the tree is immediately next to a waterway or other sensitive area. Spray until the sprayer is empty so you use all of the treatment mixture on the intended tree.

NOTE: If the spray is too foamy, you can add a cup or two of water in the sprayer tank after you've loaded the required amount of treatment mixture into it.

Step 5. When you're finished treating each tree, mark it to indicate it's been treated. Give the treatment time to dry before children or pets are allowed in the area.

CALL THE HEMLOCK HELP LINE 706-429-8010 WITH ANY QUESTIONS.



Applying Safari 20 SG by Trunk Spray – Small Custom Batch

IMPORTANT

Use the **specially marked measuring cup** that comes with your purchase of Safari to measure the required amount of product and a regular measuring cup to measure the amount of water. Note that the numbers printed on the special measuring cup refer to *ounces of weight* of Safari 20 SG and are *not* the same as *fluid ounces of volume* in a regular measuring cup.

CONVERSION FACTOR

If you don't have the special measuring cup, you can use a regular measuring cup with the following conversion factor for Safari 20 SG:

8 fl. oz. by volume in a regular measuring cup = 4 oz. by weight in the Safari measuring cup.

Wear long sleeved shirt, long pants, shoes and socks, goggles, gloves, and mask while spraying.

Step 1. Measure the trunk diameter of the tree at breast height. This is called "inches dbh."

Step 2. To make a **small custom batch of treatment mixture**, put the required amount of water in a mixing container first. Refer to the chart below. Warm water works best.

Step 3. Then add the corresponding amount of product shown in the chart below and shake until all treatment material is dissolved.

MIXING & DOSING						
Inches (DBH)	Amount of Product PER INCH	Amount of Water PER INCH				
1 - 15	0.1 oz = 3 grams	2 fluid ounces				
16 – 19	0.133 oz – 4 grams	2 fluid ounces				
20 - 23	0.167 oz = 5 grams	2 fluid ounces				
24 - 27	0.2 oz = 6 grams	2 fluid ounces				
28 - 31	0.233 oz = 7 grams	2 fluid ounces				
32 - 35	0.267 oz= 8 grams	2 fluid ounces				
36 – 39	0.3 oz = 9 grams	2 fluid ounces				
40 or greater	0.33 oz = 10 grams	2 fluid ounces				

Step 4. Treatment is done on an **individual tree** basis. Use the Dosing table below to determine how many ounces of treatment mixture the tree needs by multiplying its trunk diameter by the number of ounces shown in the right-hand column. Use a regular measuring cup to measure out exactly the required amount of treatment mixture for the tree and pour it into the sprayer.

Step 4. Set the sprayer for low pressure (10-15 psi) and adjust the nozzle for a spray about 3-4 inches wide (not a stream and not a mist). Position the nozzle 2 inches from the trunk and spray from 5 ½ feet above the ground to 6 inches above the ground. Do this very slowly to avoid back-splash and allow the treatment material to be absorbed into the bark; try not to let it drip down onto the ground if the tree is immediately next to a waterway or other sensitive area. Spray until the sprayer is empty so you use all of the treatment mixture on the intended tree.

NOTE: If the spray is too foamy, you can add a cup or two of water in the sprayer tank after you've loaded the required amount of treatment mixture into it.

Step 5. When you're finished treating each tree, mark it to indicate it's been treated. Give the treatment time to dry before children or pets are allowed in the area.

CALL THE HEMLOCK HELP LINE 706-429-8010 WITH ANY QUESTIONS.

Safari 20 SG Extended Mixing & Dosage Chart for soil Drench or Trunk Spray

Master Batch: 96 oz Mixture

Custom Batch:

96 oz water plus 10.5 oz. product

2 oz water per inch dbh" plus (oz product per inch dbh times dbh)

96 oz water plus 10.5 oz. product 2 oz water per inch dbh" plus (oz product per inch dbh times dbh)								
DBH"	Treatment	TOTAL		DBH"	Water (oz)	Product	TOTAL	TOTAL
	Mixture (oz)	Treatment			per inch dbh	(oz by weight)	Product	Treatment
	per inch dbh	Mixture (oz)	_			per inch dbh	(oz by weight)	Mixture (oz)
1	1.0	1	<u> </u>	1	2	0.1	0.1	2
2	1.0	2	<u> </u>	2	2	0.1	0.2	4
3	1.0	3	<u> </u>	3	2	0.1	0.3	6
4	1.0	4	<u> </u>	4	2	0.1	0.4	8
5	1.0 1.0	5	<u> </u>	5	2 2	0.1	0.5 0.6	10 12
6 7	1.0	6 7	<u> </u>	6 7	2	0.1 0.1	0.6	14
-	1.0	8	_	8	2	0.1	0.8	16
8 9	1.0	9	-	9	2	0.1	0.8	18
10	1.0	10	-	10	2	0.1	1	20
11	1.0	11	-	11	2	0.1	1.1	22
12	1.0	12	-	12	2	0.1	1.2	24
13	1.0	13	-	13	2	0.1	1.3	26
14	1.0	14	-	14	2	0.1	1.4	28
15	1.0	15	-	15	2	0.1	1.5	30
16	1.33	21.28	-	16	2	0.133	2.128	32
17	1.33	22.61		17	2	0.133	2.261	34
18	1.33	23.94		18	2	0.133	2.394	36
19	1.33	25.27		19	2	0.133	2.527	38
20	1.67	33.4	Ī	20	2	0.167	3.34	40
21	1.67	35.07	-	21	2	0.167	3.507	42
22	1.67	36.74	-	22	2	0.167	3.674	44
23	1.67	38.41	-	23	2	0.167	3.841	46
24	2.0	48		24	2	0.2	4.8	48
25	2.0	50		25	2	0.2	5	50
26	2.0	52		26	2	0.2	5.2	52
27	2.0	54		27	2	0.2	5.4	54
28	2.33	65.24		28	2	0.233	6.524	56
29	2.33	67.57		29	2	0.233	6.757	58
30	2.33	69.9		30	2	0.233	6.99	60
31	2.33	72.23		31	2	0.233	7.223	62
32	2.67	85.44		32	2	0.267	8.544	64
33	2.67	88.11		33	2	0.267	8.811	66
34	2.67	90.78		34	2	0.267	9.078	68
35	2.67	93.45	<u> </u>	35	2	0.267	9.345	70
36	3.0	108	<u>_</u>	36	2	0.3	10.8	72
37	3.0	111		37	2	0.3	11.1	74
38	3.0	114		38	2	0.3	11.4	76
39	3.0	117	<u> </u>	39	2	0.3	11.7	78
40	3.33	133.2	-	40	2	0.33	13.2	80
41	3.33	136.53		41	2	0.33	13.53	82
42	3.33	139.86	_	42	2	0.33	13.86	84
43	3.33	143.19	-	43	2	0.33	14.19	86
44	3.33	146.52	-	44	2	0.33	14.52	88
45	3.33	149.85		45	2	0.33	14.85	90
46	3.33	153.18		46	2	0.33	15.18	92
47 48	3.33 3.33	156.51		47 48	2	0.33 0.33	15.51 15.84	94 96
		159.84	uro into the c				to reduce foamin	

After pouring prescribed amount of mixture into the sprayer for a specific tree, add more water to reduce foaming if necessary.